

# SmartScan UDP message format

Document Ref:	7-049-3018-E
Document Date:	22 December 2014
Prepared by:	RT
Approved by:	KMJ

*This information herein is the property of Smart Fibres Ltd and is to be held strictly in confidence by the recipient. No copy is to be made without the written permission of Smart Fibres Ltd. Disclosures of any of the information herein is to be made only to such persons who need such information during the course of their engagement or employment at Smart Fibres Ltd or under the written authority of Smart Fibres Ltd.*

*Any patent applications, patents and/or design applications, registered designs or copyrights arising from or contained in the information herein, shall be considered the property of Smart Fibres Ltd and as such are subject to the aforementioned obligation of confidence on the recipient.*



Certificate No: LRQ 4003532

Smart Fibres Ltd · Brants Bridge · Bracknell · RG12 9BG · United Kingdom

Email: [info@smartfibres.com](mailto:info@smartfibres.com) · Web: [www.smartfibres.com](http://www.smartfibres.com)

Tel: +44 1344 484111 · Fax: +44 1344 486759

Directors: C Staveley · A Melrose · Registered in England: 3563533 · VAT Registration No: GB723426060  
Registered Office: 141 Dedworth Road · Windsor · Berkshire · SL4 5BB · United Kingdom

1 Overview.....	3
2 Diagnostic message.....	4
2.1 Operation.....	4
2.2 Format.....	4
2.3 Description of operational states.....	4
3 Maintenance message.....	5
3.1 Operation.....	5
3.2 Format.....	5
3.3 RFC1497 commands.....	5
3.3.1 Set commands.....	5
3.3.2 Return commands.....	8
3.4 Example maintenance message.....	9
4 Peak data.....	10
4.1 Operation.....	10
4.2 Format.....	10
5 Spectrum data.....	1
5.1 Operation.....	1
5.2 Format.....	1

Document Revision History:

Issue	Issue Date	Change
B	20 <sup>th</sup> January 2010	Updated
C	27 <sup>th</sup> April 2010	More detail added to slot set up
D	26 <sup>th</sup> August 2011	Details of RFC 1497 terminal byte added to maintenance message. Example maintenance message included.
E	22 <sup>nd</sup> December 2014	Added time of flight compensation messages and updated layout.

# 1 OVERVIEW

SmartScan communicates with its host via UDP messages over Ethernet. There are diagnostic, maintenance and data messages. Diagnostic messages contain information about the instrument's basic settings, Maintenance messages are used to set up and control the interrogator and data messages contain raw (spectral) or processed (FBG peak) data.

Many of the set up parameters as well as the peak values are expressed as "LASER channel numbers", these are multiplied by 128 to give a resolution that fits into a two byte value e.g. Channel 399 \* 128 = 51072, whereas  $2^{16} = 65536$ . Peak values are returned with a fractional portion of a whole channel when divided by 128 by the PC interface.

The wavelength range of the SmartScan is divided up into 400 channels. For a 40 nm SmartScan these are spaced at about 100 pm (12.5 GHz) and for a 35 nm SmartScan at about 88 pm (11 GHz).

Laser Channel	40 nm SmartScan		35 nm SmartScan	
0	191125.0 GHz	1568.567 nm	191680.0 GHz	1564.026
1	191137.5 GHz	1568.465 nm	191691.0 GHz	1563.936
2	191150.0 GHz	1568.362 nm	191702.0 GHz	1563.846
:				
397	196087.5 GHz	1528.871 nm	196087.0 GHz	1528.875
398	196100.0 GHz	1528.773 nm	196098.0 GHz	1528.789
399	196112.5 GHz	1528.676 nm	196109.0 GHz	1528.703

## 2 DIAGNOSTIC MESSAGE

### 2.1 OPERATION

- PC sends diagnostic query to SmartScan port 30001
- SmartScan listens for diagnostic messages on port 30001.
- SmartScan replies using port 30071 to PC port 30001
- SmartScan will use this last IP address received for all replies from now on
- PC should listen on port 30001 for replies from SmartScan

### 2.2 FORMAT

Message (from PC to SmartScan and SmartScan to PC) consists of one standard UDP datagram. The UDP payload consists of a header as follows, with no following data.

```
struct DIAG
{
    u32    ulTimeStamp;
    u8     ucDamage;           // For future use
    u8     ucState;
    u8     ucvLevel1damage[8]; // For future use
    u8     ucvLevel2damage[8]; // For future use
    u8     ucvSpare[8];       // For future use
};
```

<b>ulTimeStamp</b>	UTC timestamp based on seconds after 01:01:1970. big endian <b>PC to SmartScan:</b> PC broadcasts its UTC timestamp so that SmartScan can set its local time <b>SmartScan to PC:</b> SmartScan informs PC of what its UTC is set to, PC performs no action
<b>ucState</b>	<b>PC to SmartScan:</b> PC instructs SmartScan to go to a state (go to this state) <b>SmartScan to PC:</b> Informs PC of SmartScan's current state <b>Values:</b> 0 = No Change, 1 = STANDBY, 2 = OPERATIONAL, 3 = MAINTENANCE
<b>ucvLevel1damage[8]</b>	<b>PC to SmartScan:</b> not used <b>SmartScan to PC:</b> not used
<b>ucvLevel2damage[8]</b>	<b>PC to SmartScan:</b> not used <b>SmartScan to PC:</b> not used
<b>ucvspare[8]</b>	<b>PC to SmartScan:</b> not used <b>SmartScan to PC:</b> not used

### 2.3 DESCRIPTION OF OPERATIONAL STATES

#### No Change

Used to enquire what the current operation state is without changing it. The PC can send diagnostic messages to the SmartScan during power up to establish when it has switched to operational state.

#### Standby

This is the default state after power up, in this state the SmartScan transmits no data and will only accept and respond to diagnostic messages.

#### Operational

This is the normal running state, the SmartScan transmits data messages and can receive, process and respond to diagnostic and maintenance messages. When the SmartScan is ready it will automatically switch to operational state from standby after power up.

#### Maintenance

In this state the SmartScan will accept, process and respond to maintenance messages but will transmit no data messages

## 3 MAINTENANCE MESSAGE

### 3.1 OPERATION

- PC transmits query to SmartScan port 30070
- SmartScan listens for maintenance messages on UDP port 30070.
- SmartScan replies using port 30071 to PC port 30070
- SmartScan will use this last IP address received for all replies from now on
- PC should listen on port 30070

### 3.2 FORMAT

Message (from PC to SmartScan and SmartScan to PC) consists of one standard UDP datagram. The UDP payload consists of a header as follows, followed by a variable length data array consisting of RFC1497 formatted messages. As defined in the RFC, every message should be terminated with a 0xFF byte and the total length of the message should fall on a 4-byte boundary, to achieve this 0x00 pad bytes must be added prior to the 0xFF terminator byte.

**struct MAINT**

```
{
    u32    ulCodeStamp;
    u8     ucSpare;
    u8     ucState;
    u8     ucvOptions[1018];
};
```

<b>ulCodeStamp</b>	Fixed cookie number defining message as maintenance <b>Value:</b> 0xAA55E00E big endian
<b>ucState</b>	<b>PC to SmartScan:</b> PC instructs SmartScan to go to a state <b>SmartScan to PC:</b> Informs PC of SmartScan's current state <b>Values:</b> 1 = STANDBY, 2 = OPERATIONAL, 3 = MAINTENANCE
<b>ucvOption</b>	Variable length array of RFC formatted commands <b>PC to SmartScan:</b> Informs SmartScan to set options to the given values <b>SmartScan to PC:</b> Returned options (current settings) <b>Values:</b> Defined below

### 3.3 RFC1497 COMMANDS

These are arranged in the standard RFC format: **[cmd][nr of data bytes][...data bytes...][padding bytes][terminator byte]**. Note that all data values (2 and 4 byte) are in network order, i.e. high significant byte first. Byte defined arrays such as MAC addresses are in normal byte order.

Commands 1 to 127 are SET values. i.e. PC tells SmartScan to set some values and returns it's global values.

Commands 128 to 199 are RETURN values. SmartScan just returns it's global values.

Notes: All numbers are in decimal, except for those in "0xNN" form, which are hex.

#### 3.3.1 SET COMMANDS

Command	Bytes	Description
1	1	Set SmartScan system state. 0 = no change 1 = standby 2 = operational 3 = maintenance
2	1	Set spectrum data source. Valid range: <0..3>

- Sets which optical channel is the source of data in the spectrum data UDP message.
- 3      2      Sets rate of spectrum data UDP transmission.  
Valid range: <0..32>
- Note:** Higher number gives faster rate.
- 4      2      Set data transmission rate.  
Valid range: <0..255>  
0 = disable UDP data transmission  
N = enable UDP data transmission, set rate to 1/N scan time.
- E.g. if N = 25 and scan time is 400µs, transmission rate is 1 sample per 10ms = 400µs \* 25 (e.g. 100Hz rate).
- Note:** If LASER step period \* LASER step count \* N > 65535 the sample interval value in the data header will overflow. In that case, calculate the interval in software and ignore the header value.
- 5      2      Set Channel Format.
- b[15]    CPU read method  
          0 = Select Ch  
          1 = read all 64  
b[14]    DSP write method  
          0 = Slot address  
          1 = Contiguous  
b[13..9] Not used  
b[8..4]    Number of gratings to interrogate  
          Valid range: <1..16>  
b[3..0]    Number of optical channels to interrogate  
          Valid range: <1..4>
- Note1:** In CPU read method 0, any number of gratings <1..16> and optical channels <1..4> can be selected. In CPU read method 1, only gratings <1,2,4,8,16> and channels <1,2,4> can be selected. Method 0 is default.
- Note2:** DSP method 0 stores the FBG peaks in the order of their corresponding slot positions, i.e. the slot window must be established beforehand. DSP method 1 stores peaks contiguously.
- Note3:** The maintenance message header uses an 8 bit word format to return this code, so the "16 grating" pattern is sent as 0x0n rather than 0x10n. Better to read return CMD [133] which returns the value as a word
- 6      2      Set all four channel threshold values to same value.  
Valid range: <0..65535>
- 8      2      Set first LASER step in scan.  
Valid range: <0..399>
- There are only 400 LASER steps defined, therefore the start step plus the steps per scan defined by command 9 should be less than or equal to 400.
- 9      2      Set acquisition rate.
- Two available formats, depending on b[15]:  
if b[15]=0  
    b[2..0] LASER step count code  
        0 = 400  
        1 = 200  
        2 = 100  
        3 = 50

b[5..3] LASER step period  
     0 = 1µs  
     1 = 2µs  
     2 = 5µs  
     3 = 10µs  
     4 = 20µs  
     5 = 50µs  
 b[14..6] Not used  
 if b[15]=1  
     b[9..0] Number of steps per LASER scan  
         Valid range: <1..400>  
     b[12..10] LASER step period  
         0 = 1µs  
         1 = 2µs  
         2 = 5µs  
         3 = 10µs  
         4 = 20µs  
         5 = 50µs  
     b[14..13] Not used

18	4	Set interrogator IP address. Valid after next re-boot.
19	4	Set Subnet Mask. Valid after next re-boot.
21	4	Set Gateway IP address. Valid after next re-boot.
22	2	Set threshold for Ch0 b[15..0] Valid range <0..65535>
23	2	Set threshold for Ch1 b[15..0] Valid range <0..65535>
24	2	Set threshold for Ch2 b[15..0] Valid range <0..65535>
25	2	Set threshold for Ch3 b[15..0] Valid range <0..65535>
26	2	Write one generic slot table entry

Used to enter slot positions and manual gains

<b15..14> Optical channel  
     Valid range: <0..3>  
 <b13..12> Entry type  
     0 = slot position  
     1 = gain level  
 <b11..8> Slot number  
     Valid range: <0..15>  
 <b7..0> Data (slot position / 2 or gain level)  
     Valid range:  
         Slot position: <0..255>  
         Gain level: <0..8>

"Optical channel" defines which optical channel to apply the setting to, "entry type" defines the setting type (0 for slots, 1 for gains), "slot number" is the number of the slot either being created or the slot whose manual gain value is being set and "data" is either the end channel of the slot being defined (data = laser channel number / 2) or the gain value to apply to a previously defined slot. Slots should be defined in laser channel order. e.g. to set slot boundaries on optical channel 1 at channel 100, 200, 300 as follows:

Slot	SLOT3	SLOT2	SLOT1	SLOT0	
Laser channel	399	300	200	100	0

First set [channel 0, slot 0, type 0, data 50], then [channel 0, type 0, slot 1, data 100], then [channel 0, type 0, slot 2, data 150] the next slot should be set to the max channel - 1 (e.g. for a 400 channel scan, set slot 3 to  $399 / 2 = 199$ ), all remaining slots (4 to 15) should be set to the maximum (i.e. 255). The laser channels are zero referenced to the start channel as defined by command 8.

**Note:** Because data range is 0 to 255, when entering slot position, data is slot position / 2, e.g. for slot position 320 set data to 160

27            4        Write one slot position

<b31..24>        Not used  
 <b21..20>        Optical channel  
                      Valid range: <0..3>  
 <b19..16>        Slot number  
                      Valid range: <0..15>  
 <b15.. 0>        Slot position data  
                      Valid range: <0..399>

**Note:** Unlike command 26, the slot position does not need to be divided by 2.

29            2        Set AGC update rate

0 = disable AGC (use manual gains as set with command 26)  
 N = Enable AGC

**Note1:** Set to  $2 * \text{LASER step period in } \mu\text{s}$  (see command 9) for stable operation.

**Note2:** Lower numbers are faster.

**Note3:** When setting up manual gains, disable AGC before defining the slots and gains with commands 26 and 27.

32            4        Set SmartScan clock (UTC)

50            4        Fibre length in metres (supported in firmware version 0x1050 and above).

Used in conjunction with command 51 to compensate for time of flight delay in the fibre between the interrogators and the FBG sensors.

51            2        Fibre refractive index times 1000 (supported in firmware version 0x1050 and above).

Used in conjunction with command 50 to compensate for time of flight delay in the fibre between the interrogators and the FBG sensors.

### 3.3.2 RETURN COMMANDS

Command	Bytes	Description
129	1	SmartScan operational state (see command 1)
130	2	Spectrum data source (see command 2)
131	2	Spectra rate (see command 3)
132	2	Data rate (see command 4)
133	2	Channel format (see command 5)
134	2	Threshold level of first optical channel (see command 6)
136	2	First LASER step in scan (see command 8)



137	2	Acquisition rate (see command 9)
139	2	LASER step count (see command 9)
140	2	Software version
146	4	IP address (see command 18)
147	4	Subnet mask (see command 19)
148	6	MAC address
149	4	Network gateway (see command 21)
150	4	Fibre length (see command 50)
151	2	Fibre refractive index times 1000 (see command 51)
160	4	SmartScan clock (UTC) (see command 32)
222	4	Serial number

**Note:** Other parameters are reported but their values are not relevant to end users

### 3.4 EXAMPLE MAINTENANCE MESSAGE

**AA55 E00E 0000 0402 0000 0302 0000 0101 0200 00FF**

<b>AA55 E000</b>	Defines message as type "maintenance"
<b>00</b>	Spare byte
<b>00</b>	System State, 00 = No change
<b>04</b>	CMD = Set rate of continuous data message
<b>02</b>	Two command data bytes to follow
<b>0000</b>	Value for command is 0, = disable transmission
<b>03</b>	CMD = Set rate of scan message (used for spectrum transmission)
<b>02</b>	Two command data bytes to follow
<b>0000</b>	Value for command is 0, = disable transmission
<b>01</b>	CMD = Set system state
<b>01</b>	One command data byte to follow
<b>02</b>	Value for command is 2, = set state to operational
<b>0000</b>	Two 0x00 pad bytes in order that whole message finished on 4-byte boundary
<b>FF</b>	Terminator byte, message length = 20 bytes

This maintenance message would typically be sent at the end of an acquisition session to turn off data transmission and prevent unnecessary traffic on the Ethernet network.

## 4 PEAK DATA

### 4.1 OPERATION

- SmartScan sends using UDP port 30071 to PC port 30002
- PC should listen on port 30002 for messages
- PC does not need to transmit messages. SmartScan does not respond to PC messages

### 4.2 FORMAT

UDP payload consists of a header of 36 bytes (see below) followed by N bytes (N/2 16 bit words) of data. A payload will contain an integer number of complete scans.

Example: Take an 8 grating, 4 channel system. Each sample block will contain  $8 \times 4 = 32$  data words. Because of Ethernet size limitations, only up to 22 such sample blocks can be included in each UDP payload.

**struct DATA**

```
{
    u16    usFrameSize;           // Total number of bytes
    u8     ucHdrSize4;           // Number of bytes in header/4 (9)
    u8     ucFrameFormat;        // eg 0x84, 8gratings, 4channels
    u32    ulFrameCount;         // Incremented number
    u32    ulTimeStampH;         // UTC seconds H (scan time)
    u32    ulTimeStampL;         // UTC second L (scan time)
    u32    ulTimeCodeH;          // UTC seconds (tx time)
    u16    usTimeInterval;       // sample interval in µS, ie 400
    u16    usSpare;              //
    u16    usMinChannel;         // First LASER step, eg 0
    u16    usMaxChannel;         // Last LASER step, eg 399
    u32    ulStartFreq;          // LASER start frequency
    u32    ulStepFreq;           // LASER step frequency
};
```

<b>usFramesize</b>	Total number of bytes. <b>Value:</b> (data words * 2) + 36
<b>ucHdrSize4</b>	Number of bytes in header / 4 <b>Value:</b> 9
<b>ucFrameFormat</b>	MSB = number of gratings, LSB = number of channels. If MSB = 0 it is 16 gratings <b>Value:</b> 0x84 = 8gr/4ch, 0x04 = 16gr/4ch
<b>ulFrameCount</b>	Incremented frame count <b>Value:</b> 1,2,3....
<b>usTimeInterval</b>	Sample interval in µs, time for one scan <b>Value:</b> 400 for 400µs.
<b>usSpare</b>	Not used
<b>ulStartFreq</b>	Lowest LASER frequency (i.e. emission frequency at LASER channel 0) Start frequency (THz) = (ulStartFreq >> 16) + ((ulStartFreq & 0xFFFF) / 1000)
<b>ulStepFreq</b>	LASER step frequency (i.e. difference in emission frequency between LASER channels) Step frequency (GHz) = (ulStepFreq >> 16) + ((ulStepFreq & 0xFFFF) / 1000)
<b>Data</b>	Header is followed by 2 bytes of data per grating, per scan, representing the "channel number * 128", see section 1 Overview for more details. Note the offset from LASER channel 0 is set by maintenance command 8, if not 0, then it must be added as an offset to the data values.

In our 8gr/4ch example the data order would be:

Ch1Gr1, Ch1Gr2...Ch1Gr7, Ch1Gr8, Ch2Gr1, Ch2Gr2...Ch2Gr8, Ch3Gr1...Ch3Gr8, Ch4Gr1...Ch4Gr8  
The data order is then repeated for the 2<sup>nd</sup> to 22<sup>nd</sup> samples.

The UTC time-stamp applies to the first sample in the message, the PC can generate timestamps for the remaining samples by adding multiples of the time interval.

## 5 SPECTRUM DATA

### 5.1 OPERATION

- SmartScan sends using UDP port 30071 to PC port 30072
- PC should listen on port 30072 for messages
- PC does not need to transmit messages. SmartScan does not respond to PC messages

### 5.2 FORMAT

UDP payload consists of a header of 36 bytes (see below) followed by LASER step count words of scan data. Scan data is unsigned 16 bit words in network (big endian) format.

**struct SPECTRUM**

```
{
    u16    usFrameSize;           // Total number of bytes - 2
    u8     ucHdrSize4;           // Number of bytes in header/4 (9)
    u8     ucFrameFormat;        // Scan source optical channel
    u32    ulFrameCount;         // Incremented on every message
    u32    ulTimeStampH;         // UTC seconds H (scan time)
    u32    ulTimeStampL;         // UTC seconds L (scan time)
    u32    ulTimeCodeH;          // UTC seconds (transmit time)
    u16    usTimeInterval;       // scan time interval µs
    u16    usNrSteps;            // Steps per scan
    u16    usMinChannel;         // First LASER step
    u16    usMaxChannel;         // Last LASER step
    u32    ulUnused1;            // 0
    u32    ulUnused2;            // 0
};
```